

Analysis Tools

Analysis tools are run as part of a CyPhy test bench. Each tool defines which artifacts should be extracted from the CyPhy model and what the entry point of the tool is. To add a new analysis tool follow the instructions below.

1. Create Directory

Create a new directory at `META tool install location\analysis_tools`, e.g. `C:\Program Files (x86)\META\analysis_tools` and name it appropriately.




Figure 1: Location of new directory

2. Create `analysis_tool.manifest.json`

Add `analysis_tool.manifest.json` inside the created folder, see Figure 2. An example can be found at:

META tool install location\analysis_tools\ExamplePython\analysis_tool.manifest.json.

Note: one directory can contain multiple analysis tools.




Figure 2: Create new `analysis_tool.manifest.json`

3. Configure `analysis_tool.manifest.json`

Change the values accordingly to your needs in your `analysis_tool.manifest.json` file.




Figure 3: Configure `analysis_tool.manifest.json`

1. **key** - name of your tool
2. **version** - version number of your tool
3. **outputDirectory** - content of this directory will be copied to **every** test bench output directory where your tool is selected as the analysis tool. Note: this could override some generated artifacts, pick file names carefully.
4. **runCommand** - main entry point to your tool. It is *strongly* recommended that you use a batch file and then call python/java or other tools, see Figure 4 and 5. (For failed executions exit with error code != 0.)
5. **requiredInterpreter** - defines the ProgID of the interpreter that has to generate the input artifacts for your analysis tool. Examples
 1. `MGA.Interpreter.CyPhy2CAD_CSharp` - Generates input files for CAD processing (Assembly, FEA, CFD, Thermal, Kinematic, etc.)
 2. `MGA.Interpreter.CyPhyCADAnalysis` - Generates CAD files.
 3. `MGA.Interpreter.CyPhy2Modelica_v2` - Generates composed Modelica models.
 4. `MGA.Interpreter.CyPhyDesignExporter` - Generates an ADM (xml) file describing the design.

Note: For more than one analysis tool add an extra key-value pair.




Figure 4: Create batch file for runCommand





Figure 5: Batch file for runCommand

4. Register tools

Register all tools by running the `add_registry_entries.py` script from the META Python virtual environment as an administrator:
`..\bin\Python27\Scripts\python.exe add_registry_entries.py.`




```
Administrator: C:\Windows\system32\cmd.exe

C:\Users\Admin>cd "c:\Program Files (x86)\META\analysis_tools"

c:\Program Files (x86)\META\analysis_tools>..\bin\Python27\Scripts\python.exe add_registry_entries.py
Registering analysis tools from c:\Program Files (x86)\META\analysis_tools
  cfd_preprocessing is registered with parameters {u'version': u'5.7', u'outputDirectory': u'PreProcessing', u'requiredInterpreter': u'MGA.Interpreter.CyPhy2CAD', u'InstallLocation': 'c:\\Program Files (x86)\\META\\analysis_tools\\CFD\\CSharp', u'runCommand': u'', 'name': u'cfd_preprocessing'}
  Example is registered with parameters {u'version': u'0.1', u'outputDirectory': u'output', u'requiredInterpreter': u'MGA.Interpreter.CyPhyDesignExporter', u'InstallLocation': 'c:\\Program Files (x86)\\META\\analysis_tools\\ExamplePython', u'runCommand': u'run.cmd', 'name': u'Example'}
  FAMEBracketFatigue is registered with parameters {u'version': u'14.03', u'outputDirectory': u'output', u'requiredInterpreter': u'MGA.Interpreter.CyPhyReliabilityAnalysis', u'InstallLocation': 'c:\\Program Files (x86)\\META\\analysis_tools\\FAME', u'runCommand': u'run_FAMEBracketFatigue.cmd', 'name': u'FAMEBracketFatigue'}
  FAME is registered with parameters {u'version': u'14.03', u'outputDirectory': u'output', u'requiredInterpreter': u'MGA.Interpreter.CyPhyReliabilityAnalysis', u'InstallLocation': 'c:\\Program Files (x86)\\META\\analysis_tools\\FAME', u'runCommand': u'run_FAME.cmd', 'name': u'FAME'}
  FAMECriticalFaultCount is registered with parameters {u'version': u'00.01', u'outputDirectory': u'output', u'requiredInterpreter': u'MGA.Interpreter.CyPhy2Modelica_v2', u'InstallLocation': 'c:\\Program Files (x86)\\META\\analysis_tools\\FAMECriticalFaultCount', u'runCommand': u'run_critical_fault_count.cmd', 'name': u'FAMECriticalFaultCount'}
  FAMEFaultCount is registered with parameters {u'version': u'00.01', u'outputDir
```

Figure 6: Start registration

If it runs successfully then Analysis tool registration is done. is the last message in the console.



```
Administrator: C:\Windows\system32\cmd.exe

field_of_view is registered with parameters {u'version': u'00.02', u'outputDirectory': u'output_fov', u'requiredInterpreter': u'MGA.Interpreter.CyPhyCADAnalysis', 'InstallLocation': 'c:\Program Files (x86)\META\analysis_tools\PYTHON_RICARDO', u'runCommand': u'run_fov.cmd', 'name': u'field_of_view'}
field_of_fire is registered with parameters {u'version': u'00.02', u'outputDirectory': u'output_field_of_fire', u'requiredInterpreter': u'MGA.Interpreter.CyPhyCADAnalysis', 'InstallLocation': 'c:\Program Files (x86)\META\analysis_tools\PYTHON_RICARDO', u'runCommand': u'run_field_of_fire.cmd', 'name': u'field_of_fire'}
ergonomics is registered with parameters {u'version': u'00.01', u'outputDirectory': u'output_ergonomics', u'requiredInterpreter': u'MGA.Interpreter.CyPhyCADAnalysis', 'InstallLocation': 'c:\Program Files (x86)\META\analysis_tools\PYTHON_RICARDO', u'runCommand': u'run_ergonomics.cmd', 'name': u'ergonomics'}
transportability is registered with parameters {u'version': u'00.01', u'outputDirectory': u'output_transportability', u'requiredInterpreter': u'MGA.Interpreter.CyPhyCADAnalysis', 'InstallLocation': 'c:\Program Files (x86)\META\analysis_tools\PYTHON_RICARDO', u'runCommand': u'run_transportability.cmd', 'name': u'transportability'}
QR is registered with parameters {u'version': u'13.14', u'outputDirectory': u'output', u'requiredInterpreter': u'MGA.Interpreter.CyPhy2Modelica_v2', 'InstallLocation': 'c:\Program Files (x86)\META\analysis_tools\QR', u'runCommand': u'run_QR.cmd', 'name': u'QR'}
corrosion is registered with parameters {u'version': u'00.01', u'outputDirectory': u'output_corrosion', u'requiredInterpreter': u'MGA.Interpreter.CyPhy2CAD_CS_harp', 'InstallLocation': 'c:\Program Files (x86)\META\analysis_tools\SwRI', u'runCommand': u'run_corrosion.cmd', 'name': u'corrosion'}
Analysis tool registration is done.

c:\Program Files (x86)\META\analysis_tools>
```

Figure 7: Successful registration

5. Reference analysis tool from CyPhy (GME)

Create a Workflow, see Figure 8. Add Task and select the interpreter (as defined by requiredInterpreter), see Figure 9.

Double click on the Task object in the Workflow definition and select your tool from the drop down list, see Figure 10.




Figure 8: Create Workflow and Task




Figure 9: Selected Interpreter for Task




Figure 10: Set Analysis Tool for Task

6. Executing Test Bench

Create a reference to the Workflow from a Test Bench, see Figure 11.

Run the test bench using the **MasterInterpreter** and the **JobManager** configured for local execution, see Figure 12 and 13.

While existing with error code 0 the result will be reported as **Succeeded**, see Figure 14.




Figure 11: Reference Workflow from Test Bench





Figure 12: MasterInterpreter Dialog



JobManager Configuration

☐ Remote Execution

VehicleForge URL
 Open link

User ID


Password

On success

- ☒ Wipe workspace
- ☒ Delete job

Run

Figure 13: JobManager Dialog



JobManager (Port:35010)

Id	Title	Test Bench Name	Status	Pro...	Command
0	CyPhyDesignExporter_DesignContain...	TestBench	Succeeded		run.cmd

Configured for local execution.

Figure 14: JobManager Job Status